














# COVID 19 PPE REQUIREMENTS

3/23/20

<p><b>SCREENING AT ENTRANCES</b></p>	<ul style="list-style-type: none"> <li>• Surgical Mask if unable to maintain 6 feet social distancing</li> <li>• Gloves ONLY if changed between patients</li> <li>• Gloves are NOT to be worn all day</li> <li>• Hand Hygiene between patients</li> </ul>	 
<p><b>POSITIVE SCREEN TO INITIAL SCREENING QUESTIONS</b></p>	<ul style="list-style-type: none"> <li>• Patient to dedicated isolation room</li> <li>• Sign up, door shut</li> <li>• Staff who are performing nasopharyngeal swab testing:             <ul style="list-style-type: none"> <li>• Gloves, gown, eye protection, N95 mask/PAPR</li> </ul> </li> </ul>	<p>PLEASE DO NOT ENTER WITHOUT CONTACTING UNIT MANAGER</p>   
<p><b>PERSON ADMITTED UNDER INVESTIGATION Droplet Precautions</b></p>	<ul style="list-style-type: none"> <li>• Special isolation sign</li> <li>• Gloves</li> <li>• Gown</li> <li>• Eye protection</li> <li>• Face mask</li> </ul>	   
<p><b>PERSON ADMITTED UNDER INVESTIGATION AND /OR POSITIVE Aerosolized procedures</b></p>	<p>Respirators (N-95, PAPR, or equivalent) <b>ARE ONLY INDICATED DURING PROCEDURES WHICH ARE AEROSOL-INDUCING.</b> Examples: obtaining a nasopharyngeal swab, endotracheal intubation, mechanical ventilation, aspiration of a tonsillar abscess etc. These patients require placement in a negative air pressure room.</p> <p>Negative airflow room, special isolation sign, gloves, gown, eye protection, N95/PAPR</p>	   

# SPECIAL PRECAUTIONS

Only essential personnel should enter this room




Visitors, check with staff before entry



Hand Hygiene In & Out of Room



Surgical mask required



Wear eye protection (face shield or goggles)



Gown

Gown



GLOVES

Gloves



Surgical mask on patient if out of room



**KEEP DOOR CLOSED**

When performing aerosolizing procedures, a fit tested N-95 with eye protection or PAPR is required



Staff are to utilize the N95 mask until it is visibly soiled. Inspect the mask throughout the shift

